



PC Tools

# User Manual

Issue 04

Date 2013-09-25

**Copyright © HiSilicon Technologies Co., Ltd. 2012-2013. All rights reserved.**

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of HiSilicon Technologies Co., Ltd.

## **Trademarks and Permissions**



**HISILICON**, and other HiSilicon icons are trademarks of HiSilicon Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

## **Notice**

The purchased products, services and features are stipulated by the contract made between HiSilicon and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

## **HiSilicon Technologies Co., Ltd.**

Address: Huawei Industrial Base  
Bantian, Longgang  
Shenzhen 518129  
People's Republic of China

Website: <http://www.hisilicon.com>

Email: [support@hisilicon.com](mailto:support@hisilicon.com)



# About This Document

## Purpose

The PC Tool is used to adjust the images processed by the image signal processor (ISP) during secondary development. Its component ISP tool supports previewing, snapshot, and recording. It also allows you to set ISP parameters and obtain parameter values by using the ISP control component. After setting ISP parameters, you can preview images.

## Related Version

The following table lists the product version related to this document.

Product Name	Version
Hi3518	V100



## Intended Audience

This document is intended for:




- Technical support personnel
- Software development engineers

## Symbol Conventions

The symbols that may be found in this document are defined as follows.

Symbol	Description
 <b>DANGER</b>	Alerts you to a high risk hazard that could, if not avoided, result in serious injury or death.
 <b>WARNING</b>	Alerts you to a medium or low risk hazard that could, if not avoided, result in moderate or minor injury.



Symbol	Description
 <b>CAUTION</b>	Alerts you to a potentially hazardous situation that could, if not avoided, result in equipment damage, data loss, performance deterioration, or unanticipated results.
 <b>TIP</b>	Provides a tip that may help you solve a problem or save time.
 <b>NOTE</b>	Provides additional information to emphasize or supplement important points in the main text.

## Change History

Changes between document issues are cumulative. Therefore, the latest document issue contains all changes made in previous issues.

### Issue 04 (2013-09-25)

This issue is the fourth official release, which incorporates the following changes:

#### Chapter 3 Using the ISP Tool

The screenshot of the ISP main window is changed.

The screenshot of the **IspControl** dialog box is added.

The descriptions of ISPControl gamma is updated.

The descriptions of ISPControl FPN is added.

### Issue 03 (2013-06-30)

This issue is the third official release, which incorporates the following changes:

#### Chapter 2 Installing the ISP Tool

The steps of installing the ISP tool on the board are updated.

#### Chapter 3 Using the ISP Tool

In section 3.5, the 10-bit raw data snapshot is added.

In section 3.6.1, the GUI of the ISP Control is updated.

### Issue 02 (2013-03-31)

This issue is the second official release, which incorporates the following changes:

#### Chapter 3 Using the ISP Tool

In section 3.5, the descriptions of YUV snapshots are added.

In section 3.6.1, the **IspControl** dialog box is modified.



## **Issue 01 (2013-02-05)**

This issue is the first official release, which incorporates the following changes:

### **Chapter 3 Using the ISP Tool**

In section 3.5, the descriptions of JPEG snapshots are added.

In section 3.6.1, the **IspControl** dialog box is modified.

## **Issue 00B03 (2012-11-25)**

This issue is the third draft release, which incorporates the following changes:

### **Chapter 2 Installing the ISP Tool**

Step 5 is deleted and the descriptions of step 4 are added.

## **Issue 00B02 (2012-10-30)**

This issue is the second draft release, which incorporates the following changes:

### **Chapter 3 Using the ISP Tool**

In section 3.5, the note for selecting the snapshot format is updated.

## **Issue 00B01 (2012-09-20)**

This issue is the first draft release.



# Contents

---

About This Document.....	i
1 Introduction to the ISP Tool .....	1
2 Installing the ISP Tool .....	2
3 Using the ISP Tool .....	3
3.1 Component Descriptions .....	3
3.2 GUI.....	3
3.3 Preview.....	5
3.4 Record .....	7
3.5 Snapshot.....	7
3.6 Picture Control .....	9
3.6.1 ISP Control.....	10
3.6.2 Statistics .....	14
3.7 Setting .....	15



## Figures

<b>Figure 3-1</b> HiPCTools components .....	3
<b>Figure 3-2</b> Login dialog box.....	4
<b>Figure 3-3</b> Home screen .....	4
<b>Figure 3-4</b> Preview menu .....	5
<b>Figure 3-5</b> 100% preview window .....	6
<b>Figure 3-6</b> 50% preview window .....	7
<b>Figure 3-7</b> Snapshot menu (in raw data format).....	8
<b>Figure 3-8</b> Whether to stop previewing for taking a snapshot.....	8
<b>Figure 3-9</b> Snapshot menu (in JPEG format) .....	9
<b>Figure 3-10</b> Snapshot menu (in YUV format) .....	9
<b>Figure 3-11</b> Control submenus .....	9
<b>Figure 3-12</b> IspControl dialog box .....	10
<b>Figure 3-13</b> Setting the gamma curve.....	12
<b>Figure 3-14</b> Gamma table.....	13
<b>Figure 3-15</b> FPN.....	14
<b>Figure 3-16</b> Histogram tab page.....	15
<b>Figure 3-17</b> Setting dialog box.....	16



# 1 Introduction to the ISP Tool

---

The PC Tool is used to adjust the images processed by the ISP during secondary development. Its component ISP tool supports previewing, snapshot, and recording. It also allows you to set ISP parameters and obtain parameter values by using the ISP control component. After setting ISP parameters, you can preview images.

The ISP parameters include **Exposure**, **White Balance**, **Focus**, **Iris**, **Firmware**, **Gamma**, **Shading**, **Sharpen**, and **Denoise**.





## 2 Installing the ISP Tool

---

You can install the ISP tool on the PC or board.

- To install the ISP tool on the PC, double-click **HiPCTools\_Setup.exe**, and install it by following the installation wizard.
- To install the ISP tool on the board, perform the following steps:

**Step 1** Load all .ko drivers in the Hi3518 software development kit (SDK) on the board. For details, see the *Description of the Installation and Upgrade of the Hi3518 SDK.txt*.

**Step 2** Decompress **HiPCTools\_Board.rar** to a directory of the network file system (NFS).

**Step 3** On the command line interface (CLI), enter **mount -t nfs -o nolock -o tcp,rsize=1024 xx.xx.xx.xx:/Development directory name/mnt**.

**Step 4** In the **release\_hi3518** directory, run the **HiIspTool.sh** script by running the following commands:

```
/ HiIspTool.sh sns_name image_size sns_mode
```

```
image_size: 720p|1080p|1.3m|3m|5m
```

```
sns_mode : wdr|line
```

```
eg:
```

```
ar0130 720p line
```

```
ar0130 1.3m line
```

```
9m034 720p line|wdr
```

```
ov9712 720p line
```

```
mn34031 720p line
```

```
icx692 720p line
```

```
imx104 720p line
```

```
imx122 1080p line
```

```
SOIH22 720p line
```

```
imx138 720p line
```

```
ov2710 1080p line
```

```
(To use the AR0130 sensor, run ./HiIspTool.sh ar0130 720p line.)
```

**----End**




# 3 Using the ISP Tool

## 3.1 Component Descriptions

After **HiPCTools\_Setup.exe** is installed, three components are displayed, as shown in [Figure 3-1](#).

- ITTP\_Stream: the main program. It provides various functions including stream on demand, recording, snapshot, image control, and statistics.
- ITTP\_IspControl: a dedicated tool for controlling and adjusting image quality. The **ISP control** menu of the ITTP\_Stream can be used to control images. For details, see section [3.6 "Picture Control."](#)
- ITTP\_Player: a player. It plays the H.264 streams recorded by ITTP\_Stream.


**Figure 3-1** HiPCTools components



## 3.2 GUI

After the ITTP\_Stream starts, the **Login** dialog box shown in [Figure 3-2](#) is displayed.


**Figure 3-2** Login dialog box



Enter the IP address of the board to be connected, select the version of the board to be connected, and click **OK**. The system checks whether a valid board can be connected.

- If the ISP tool does not start, or the IP address is invalid, a status message (marked with 8) shown in [Figure 3-3](#) is displayed.
- If a board is successfully connected, click **OK**. Then the home screen shown in [Figure 3-3](#) is displayed.

**Figure 3-3** Home screen



The following describes the functions of buttons, menus, or areas on the home screen:

**NOTE**


For details about functions, see the following sections.

- 1: Preview
- 2: Record
- 3: Snapshot
- 4: Control
- 5: Setting
- 6: Preview window scale
- 7: Preview window
- 8: Current status
- 9: IP address for the board over which the current video is transferred

## 3.3 Preview

The preview menu shown in [Figure 3-4](#) (marked with 1 in [Figure 3-3](#)) is used to select the preview mode or stop previewing. Two preview modes, H264 live mode and YUV live mode, are supported.

**Figure 3-4** Preview menu



When the ISP tool starts, it connects to the board whose IP address is entered in the login dialog box. The connection status is displayed in the lower left corner (marked with 8 in [Figure 3-3](#)). A video is displayed in the preview window (marked with 7 in [Figure 3-3](#)) after successful connection.


**NOTE**


- The H264 live mode is selected by default when a video starts to play.
- The YUV images are processed by the ISP.

The **Preview Window Scale** drop-down list (marked with 6 in [Figure 3-3](#)) allows you to select a scale. The scale of 30%, 50%, 80%, or 100% is supported. If the video cannot be completely displayed, drag the scroll bars or drag the lower right corner of the preview window. [Figure 3-5](#) and [Figure 3-6](#) show the preview windows when the scale is 100% and 50% respectively.






**Figure 3-5** 100% preview window



**Figure 3-6** 50% preview window

## 3.4 Record

Click the **Record** button (marked with 2 in [Figure 3-3](#)) to start or stop recording. If you click the **Record** button when a video is being played normally, recording starts and the button changes to . If you click , recording stops, and the button is restored to .

To set a save path for the recorded videos, click the **Setting** button (marked with 5 in [Figure 3-3](#)).



### NOTE

Recording is not supported in YUV live preview mode.

## 3.5 Snapshot

Snapshots can be taken from videos in raw data, JPEG, or YUV format.

- Snapshots taken from the videos in raw data format



## CAUTION

Snapshots can be taken from the videos in raw data format that are not processed by the ISP.


Click the **Snap** button (marked with 3 in [Figure 3-3](#)) to take snapshots in the background and send back data. The snapshots can be in 8-bit, 10-bit, or 12-bit raw data format, as shown in [Figure 3-7](#).



## NOTE

Select the raw data snapshot format based on the application scenario. For example, select the 12-bit format for parameter correction and select the 8-bit format for fault locating.


**Figure 3-7** Snapshot menu (in raw data format)



## CAUTION

Previewing is stopped when snapshots are taken from the videos in raw data format. When you click the Snap button, a dialog box shown in [Figure 3-8](#) is displayed, asking you whether to stop previewing for taking a snapshot.

**Figure 3-8** Whether to stop previewing for taking a snapshot




If you click **OK**, previewing stops, a snapshot is taken, and a dialog box is displayed, asking you to specify a save path and enter a file name. The snapshot information is displayed in the lower left corner marked with 8 in [Figure 3-3](#)).

When snapshots are being taken, the snapshot menus, **Preview** button, and **Basic Picture Control** menu are unavailable until snapshot taking is complete.

- Snapshots taken from videos in JPEG format

Click **Snap**, and choose **Snap JPEG** from the Snapshot menu to take snapshots in the background, and the on-demand screen is not affected.


**Figure 3-9** Snapshot menu (in JPEG format)



- Snapshots taken from the videos in YUV format

Click **Snap**, and choose **Snap JPEG** from the Snapshot menu to take YUV snapshots in the background, and the on-demand screen is not affected. The YUV snapshots are processed by the ISP but are not encoded.


**Figure 3-10** Snapshot menu (in YUV format)



## 3.6 Picture Control

The **Control** menu  (marked with 4 in [Figure 3-3](#) includes the **ISP Control**, **Statistical**, and **Download/Upload Config File** submenus, as shown in [Figure 3-11](#).

**Figure 3-11** Control submenus








### 3.6.1 ISP Control

The ISP Control tool connects to the board over the User Datagram Protocol (UDP). You can adjust the values of picture quality parameters in the **IspControl** dialog box shown in [Figure 3-12](#). The **IspControl** dialog box has multiple tab pages. When you move the pointer over a tab page name, the corresponding page is displayed. Each time a parameter is set, the status bar on the bottom shows whether the setting is successful.








**Figure 3-12** IspControl dialog box



The tab pages include **ModuleControl**, **Exposure**, **Exposure Status**, **Auto Exposure Weight**, **White Balance**, **Focus Settings**, **Iris Settings**, **Gamma**, **Shading**, **Sharpen**, **CCM**, **SaturationEx**, **Denoise**, **WDR**, **Defect Pixel**, **QueryInnerStateInfo**, **Demosaic**, **General Function I**, **General Function II**. The following describes their functions:

- **ModuleControl**: Allows you to control the module.
- **Exposure**: Allows you to set the automatic and manual exposure parameters and set the permission on exposure areas.



- Exposure Status: Allows you to set the parameters such as **AE Target Histogram** and **Average Lum.**
- Auto Exposure Weight: Allows you to obtain exposure attributes.
- White Balance: Allows you to set the white balance status parameters, red-green (RG) strength, and blue-green (BG).
- Focus Setting: Allows you to set the parameters such as **Auto/Manual Focus** and **Focus Status Info.**
- Iris Settings: Allows you to set iris control parameters.
- Gamma: Allows you to set the gamma curve (see [Figure 3-13](#)) and gamma table (see [Figure 3-14](#)).
  - There is no limitation on the number of curve points.
  - Right-clicking the mouse cancels the current point.
  - Pressing the arrow keys slightly adjusts the current point.
  - When a curve is dragged, the data is displayed in the right table in real time, and the board is configured based on the data.
  - CURVE\_USER\_DEFINE is a user-defined mode in which you can modify the curve, the other modes such as CURVE\_1\_6 are fixed modes.
  -  button: Clicking this button generates a curve on the left based on the 257 points in the gamma table.
  -  button: Clicking this button to generate data in the gamma table on the right based on the left gamma curve.
  -  button: After you modify the data in the gamma table, clicking this button configures the board based on the modified data.
  -  button: Clicking this button displays the data in the gamma table in hexadecimal format.
  -  button: Clicking this button displays the data in the gamma table in decimal format.
  -  button: Clicking this button saves the data in the gamma table as a .txt file.
  -  button: Clicking this button loads data from a .txt file to the gamma table.
- Shading: Allows you to set lens shading correction parameters.
- Sharpen: Allows you to set the sharpening parameters and edge enhancement parameters before encoding.
- CCM: Allows you to set lens shading correction parameters.
- SaturationEx: Allows you to set the color saturation parameters.
- Denoise: Allows you to set denoising parameters.
- WDR: Allows you to set WDR parameters.
- Defect Pixel: Allows you to set defect pixel correction parameters.
- QueryInnerStateInfo: Allows you to query ISP information.
- Demosaic: Allows you to implement the demosaic function.



- General Function I: Includes chrominance and luminance interference, anti-fog, and anti-false color.
- General Function II: Includes anti-flicker.
- FPN: Clicking this button sets the fixed pattern noise (FPN) mode. Set **AgainMax**, **DgainMax**, and **ISPDGainMax** to generate a YUV snapshot file. Set FPN parameters, as shown in [Figure 3-12](#). Manually input the values of **AgainMax**, **DgainMax**, and **ISPDGainMax** and click **Next**, as shown in [Figure 3-15](#).



## CAUTION

FPN processing takes about 90s.

**Figure 3-13** Setting the gamma curve








Figure 3-14 Gamma table





**Figure 3-15** FPN




### 3.6.2 Statistics

When you choose **Statistics**, a statistics window is displayed. [Figure 3-15](#) shows the statistics on the decoded Y, R, G, and B components in histograms.

When you move the pointer over the video, the current RGB information is displayed in the status bar at the bottom of the main window. The information helps you to adjust the picture quality.

**Figure 3-16** Histogram tab page



## 3.7 Setting




Click the **Setting** button (marked with 5 in [Figure 3-3](#)) to change the IP address the board that transfers the video or change the save path for recorded videos. Note that the port number of the board cannot be changed.

After the IP address changes, video previewing stops, and the new IP address is verified. If the network is normal, click **OK** to close the **Setting** dialog box, and choose a preview mode to connect the PC to the board again.

The current connection status is displayed in the area marked with 8 in [Figure 3-3](#), and the IP address is displayed in the area marked with 9 in [Figure 3-3](#). If the new IP address is invalid, a message is display in the lower left corner, as shown in [Figure 3-16](#).



**Figure 3-17** Setting dialog box



The image shows a 'Setting' dialog box with a title bar containing the text 'Setting' and a close button (X). The dialog box has a light blue background. It contains three input fields: 'IP Address:' with the value '10 . 67 . 208 . 172', 'Port:' with the value '80', and 'Rec Path:' with the value 'C:\'. To the right of the 'Rec Path:' field is a 'Browse' button. At the bottom right of the dialog box are 'OK' and 'Cancel' buttons. The 'Cancel' button is outlined with a dashed border.

Setting	X	
IP Address:	10 . 67 . 208 . 172	
Port:	80	
Rec Path:	C:\	Browse
OK		Cancel